Slotting

A Slot is a location in a Zone large enough for one Volume. Slotting is a process of allocating a [master:volumes|Volume]] to a particular slot to allow documentation of the exact storage location of that [master:volumes|Volume]].


Adding Slots to a Repository

To add Slots to a Repository, create a Zone using the Zone Administration tool in the Administration Menu. Then, follow the steps to Add a Zone to a Repository.

Manually Add a Volume to a Slot

To manually add a [master:volumes|Volume]] to a Slot, double-click a Volume in the [master:volumes|Volume]] List or right-click a Volume in the Volume List and select **Properties**. This will launch the Volume Properties Window.

Select the **Target Location** tab and enter a Slot number in either the `Slot field` in the Relative Location window or the `Level field` and `Slot field` in the Absolute Location window.



Click Save and the Volume will be put into a Move to that slot, even if that Volume is moving to a Slot within its Current Repository.

Press F5 in the inventory window to update the display to show new target slotting.

Automatic Slotting

Automatic Slotting in TapeTrack is done with a Command Line program called TMSS10SlotAllocation that is included in installs of TapeTrack Framework Server and TapeTrack Server Utilities in conjunction with Windows Task Scheduler.


TMSS10SlotAllocation must be run on the TapeTrack Framework Server, but it can be launched remotely if necessary.

Sample Slotting Script

<sxh> TMSS10SlotAllocation -S user:-password@tapetrack.domain.com > “%TMSS10REPORTS%\slotting_report.txt” 2> “%TMSS10REPORTS%\slotting_error.txt” </sxh>

Preparing TapeMaster for Automatic Slotting

Before running TMSS10SlotAllocation , Repositories must be set so that Slotting is Enabled. This can be done under the Options Tab of the Repository Properties Window.



Once **Slotting** is enabled, the slotting Assignment Options can be set.

- **Slotting Mode**
  - **IntelliSlot**: The Slotting batch process will Slot Volumes in groups by Consignment or Slotting Order until the available group slots are filled. At this point, empty Slots will be filled on a First Available Status.
  - **First Available**: Volumes will be put in the first available Slot in their Repository and will not be grouped.
  - **Bypass**: When Volumes are automatically confirmed (see above), they will not be assigned Slots.
- **Ignore Home Slot**: If a Volume has been assigned a Home Slot in the Options Tab of the Volume Properties Window, this Repository will ignore it and Slot using the Slot assignment Options.
- **Do not reslot**: If set to true a [master:volumes|Volume]] will not be reslotted in it's previous slot when it is moved back.
- **Retain moving slot**: If set to true the slot allocation is not made available for other

[master:volumes|Volumes]] until the [master:volumes|Volumes]] moving out is confirmed at target location. False allows the slot to be allocated to another [master:volumes|Volume]] as soon as the occupying [master:volumes|Volume]] is placed in a move status.

- **Slotting Order**: There are three orders with which [master:volumes|Volumes]] may be assigned Slots:
  - **Movement Time**: [master:volumes|Volumes]] will be assigned Slots based on when they arrived at the selected Repository.
  - **From Location**: [master:volumes|Volumes]] will be assigned Slots based on which Repository they were sent from.
  - **Volume-ID**: [master:volumes|Volumes]] will be assigned Slots in the alphanumeric order based on their [master:volumes|Volume-ID's]].

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/master/slotting?rev=1566186309

Last update: **2025/01/21 22:07**