Enabling Replication

To enable TapeTrack High Availability Replication:


Steps On Remote Server

Install the TapeTrack Framework Server software on your remote machine.


Stop the service on the remote machine.

Delete all database files on the remote machine (all files in the `var/db` directory EXCEPT the DB_CONFIG file).

Do Not delete the DB_CONFIG file.



Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 0** to make the machine a Replicant.




Edit the Replicant Server and Master Server host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com** with the IP address of **your** Replicant Server (RRR.RRR.RRR.RRR used as Replicant IP example).
- Replace **master.tapetrack.com** with the IP address of **your** Master Server (MMM.MMM.MMM.MMM used as Master IP example).



Ensure you use the IP4 address for the Master and Replicant Server as using the domain name can cause issues with the IP6 address replacing the IP4 address, stopping the Master and Replicant communication.





Ensure that the replication TCP/IP ports specified in the DB_CONFIG file are open for inbound connections.

Start the TapeTrack service on the remote machine.


Steps On Master Server

Stop the TapeTrack service on the master TapeTrack server.




Do Not delete any files on the master server

Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 1** to make the machine a master server.



Edit the DB_CONFIG file to define the local and remote server. Edit the Replicant Server and Master Server host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com** with the domain name (or IP address) of **your** Replicant Server (RRR.RRR.RRR.RRR used as Replicant IP example).
- Replace **master.tapetrack.com** with the domain name (or IP address) of **your** Master Server (MMM.MMM.MMM.MMM used as Master IP example).





Ensure that the replication TCP/IP ports are open for inbound/outbound connections.

Start the master TapeTrack Server.

Confirming Functionality Of Primary And Replicant Servers

Open `$DB_Msg.txt` file (in the `var/db` directory) on both the primary and replicant server to ensure that replication is functional.



Ensure that all firewall ports are open to allow the replication traffic to pass between the replicants.



The replication communications are not encrypted so if replication is enabled you should ensure that all machines that are replicated are in a trusted network or connected via a secure VPN connection.

Server replication troubleshooting

See Also

Restoring replicant server to master server status

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/server/replication?rev=1578443426

Last update: **2025/01/21 22:07**