

Repository Options

The [Repository](#) options allow fine tuning of a [Repositories](#) behaviour to match your processes of [Volume](#) Management.

GUIDs	
Local	55533033-0000-0000-4c54-4f004f464653
Remote	00000000-0000-0000-0000-000000000000
Allowable Volume-IDs	
Type	Vault
Scratch Mode	No Change
Scratch Priority	0
Offsite	True
Primary	False
No Distribution	False
Internal	False
Sort Sequence	0
Force Simple Management	False
No Next Repository	False
Allow Deletes	False
Allow Overlaps	False
De-assign from Container	False
Empty Container	False
Do not slot if Container	False
Do not slot	False
Require Tag	False
Require Tag Reset	False
No re-move	False
Disallow backward next move date changes	False
Reset Data Cluster	False
Confirm Container Contents	False
Move Container Contents	False
Late Threshold	0
Highwater Offset	0

Buttons: Save, Cancel, Help

To open the [Repository](#) options, right-click a [Repository](#) and select properties or double click the [Repository](#) and select the options tab.

Allowable Volume-ID's

When left blank, [Volumes](#) with any allowable characters can be added to this [Repository](#). [Filters](#) can be added to force all new [Volumes](#) added to conform to certain criteria.

Adding ??????L? will force all new [[object:volume|Volumes]] to have 8 characters including an L in the 7th position.

Adding US* will force all new `[[object:volume|Volumes]]` to start with a US prefix.

Type

Select [Type](#) of [Repository](#) to change display icon to match [Repository](#) function.

The options are:

-  Destruction
-  Disaster Recovery
-  Legal Hold
-  Library
-  Ordered
-  Rack
-  Scratch
-  Transport
-  Vault

Scratch Mode

- No Change: No change to the [Volumes](#) scratch status
- Scratch: Adds a [Scratch flag](#) to the [Volume](#) when placed in a move status to this [Repository](#)
- Un-scratch: Removes a [Scratch flag](#) from a volume when placed in a move status to this [Repository](#)

Scratch Priority

- Scratch selection priority (0=do not consider).

Offsite

- This [Repository](#) is considered to be offsite when set to True.

Primary

- This [Repository](#) is considered to be the Primary [Repository](#) when set to True. It marks that repository as the organisation's main operational location—usually the tape library or data centre where tapes are created, used, or returned from offsite storage. It is primarily a classification flag. Setting it to True does not itself:
 - Make it the default repository for new tapes.
 - Automatically move tapes there.
 - Change the repository's Next Repository.
 - Affect slotting, scratch status, or movement rules.

No Distribution

- When picking a volume that is destined for this [Repository](#), confirm the movement when set to true.

Internal

- This [Repository](#) has an internal purpose and should not be displayed in all applications when set to True.

Sort Sequence

- The order in which this [Repository](#) will be displayed (0=first, 255=last) in the [Repository](#) window.

Force Simple Management

- When a [Volume](#) moves to this [Repository](#) always force [Simple Management](#) when set to True.

No Next Repository

- When set to True this [Repository](#) can be saved even though it may have no Next Repository.

Allow Deletes

- When set to True, Users with alter privileges can delete [Volumes](#) in the selected [Repository](#).

Allow Overlaps

- When set to True this will allow internal overlapping Zone locations to be assigned to this [Repository](#).

De-assignment from Container

- When set to True Any volume confirmed at this [Repository](#) will be unassigned from its Container.

Empty Container

- When set to True all [Volumes](#) will be unassigned from a container when confirmed at this [Repository](#).

Do not slot if Container

- When set to True it will add a “Do Not Slot” option to a Container when it is moved to this [Repository](#).

Do not slot

- When set to True it will add a “Do Not Slot” option to any [Volume](#) when it is moved to this [Repository](#).

Require Tag

- When set to True a Require a Tag value will be set for any [Volume](#) moving to this [Repository](#).

Require Tag Reset

- When set to True a Require a Tag value to be confirmed before a [Volume](#) can be confirmed out of this [Repository](#).

No re-move

- When set to True a [Volume](#) will not be allowed to be moved to another [Repository](#) until it is confirmed in this [Repository](#).

Disallow backward next move date changes

- When set to True disallow any update to the move date of a [Volume](#) that is today or earlier.

Reset Data Cluster

- When set to True this will reset the [Data Cluster](#) of any [Volume](#) confirmed to this [Repository](#).

Confirm Container Contents

- When set to True this will confirm the Container contents for this [Repository](#).

Move Container Contents

- When set to True this will move Containers contents when moved to this [Repository](#).

Late Threshold

- When a Late Threshold is set for this [Repository](#) a [Volume](#) will be flagged as late if the time it remains in a move status exceeds this value (600=600 minutes or 10 hours).

Highwater offset

- When [Slotting](#) is set to use IntelliSlot (see below), the automatic [Slotting](#) process will group Volumes together in Zones based on the [Slotting](#) Order (see below) until the Slot Number matches the [Highwater offset](#). At this point, IntelliSlot will stop grouping [Volumes](#) and will put them wherever a Slot is available.

Movement Mode

- Automatically Confirm.
- Bypass and move to Next [Repository](#).
- Automatically Confirm then move it to the next [Repository](#).

Next Repository

- Relates to the [Repository](#) a [Volume](#) will move to after it has been in this [Repository](#).

Enable Slotting

- When set to True, Volumes moving to this [Repository](#) will be assigned a [slot](#).

Capacity Sets the maximum number of [Volumes](#) that can be confirmed or in a Move Status to the selected [Repository](#) at any given time.

- In Use
- Incoming
- Outgoing
- Minimum Scratch
- Scratch

Coordinates

Coordinates can be entered for the geographic location of this [Repository](#).

- Latitude
- Longitude

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://docs.tapetrack.com/master/repository_options?rev=1787815067

Last update: **2026/08/27 07:17**

