Enabling Replication

To enable TapeTrack High Availability Replication:

Steps On Remote Server


Install the TapeTrack Framework Server software on your remote machine.

Stop the service on the remote machine.


Delete all database files on the remote machine (all files in the `var/db` directory except the DB_CONFIG file).



Do Not delete the DB_CONFIG file.




Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 0** to make the machine a Replicant.



Edit the replication local (replicant server) and remote (master server) host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com 5010** with the domain name (or IP address) of **your** replicant server.
- Replace **master.tapetrack.com 5010** with the domain name (or IP address) of **your** master server.





Ensure that the replication TCP/IP ports specified in the DB_CONFIG file are open for inbound connections.

Start the TapeTrack service on the remote machine.


Steps On Master Server

Stop the TapeTrack service on the master TapeTrack server.




Do Not delete any files on the master server

Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 1** to make the machine a master server.



Edit the DB_CONFIG file to define the local and remote server. Edit the replication local (master server) and remote (replicant server) host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com 5010** with the domain name (or IP address) of **your** replicant server.
- Replace **master.tapetrack.com 5010** with the domain name (or IP address) of **your** master server.





Ensure that the replication TCP/IP ports are open for inbound/outbound connections.

Start the master TapeTrack server.

Confirming Functionality Of Primary And Replicant Servers

Open `$DB_Msg.txt` file (in the `var/db` directory) on both the primary and replicant server to ensure that replication is functional.



Ensure that all firewall ports are open to allow the replication traffic to pass between the replicants.



The replication communications are not encrypted so if replication is enabled you should ensure that all machines that are replicated are in a trusted network or connected via a secure VPN connection.

Server replication troubleshooting

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/server/replication?rev=1531902990

Last update: **2025/01/21 22:07**