
# Preferences

The Preferences window, `File` → `Preferences`, sets basic customization for TapeMaster such as sounds, hidden objects, etc.




## Options

- **Disable sounds**: If set to `True`, sounds in TapeMaster will be muted.
- **Case Insensitive Filters**: Case is ignored when matching strings against filters.
- **Show hidden Customers**: If set to `True`, the Customer Tree will display Customers that have the `Hide Customer` option in the Customer Properties Window set to `True`.
- **Show hidden Media**: If set to `True`, the Customer Tree will display Media Types that have the `Hide Media Type` option in the Options Tab of the Media Type Properties Window set to `True`.
- **Show hidden Volumes**: If set to `True`, the Volume List will display Volumes that have the `Hide Volume` option in the Options Tab of the Volume Properties Window set to `True`.
- **Parent/Child**: If set to `False`, the Customer Tree will not display Customers with a Parent Customer set in the Customer Properties Window nested under their Parent Customer.
- **Anonymous Customers**: If set to `True`, Customer Descriptions in the Customer Tree will not display.

- **Enable Consignment Tab**: If set to `True`, the Consignments tab will appear as an Administration Tab.
- **Repository-ID filters**: If set to `True`, Volumes in the Volume List can be filtered by the Repository-ID instead of the Repository Description.
- **Disable Volume List inline edit**: If set to `True`, inline editing in Volume List will be disabled. (Requires restart)
- **Volume List Above Repository List**: Reorganize Volume and Repository windows in the GUI. `True` = Volumes displayed above Repositories. `False` = Repositories above Volumes.
- **Location Auto Swap**: If set to `True`, will display the Volume slot location instead of slot number if inventory quantity is under the `Location Auto Swap Max` value.
- **Location Auto Swap Max** sets the maximum number of Volumes to enable the `Location Auto Swap` function. This field only displays when `Location Auto Swap` is set to `True`.
- **Show Volume Refresh Clock**: If set to `True` a counter will display the time in seconds from the last time the Volume window was refreshed. Changes will take effect on restart of TapeMaster.
- **Show Volume Health Score**: Display the Library Health Score in the `Volume Properties` window.
- **Volume Description Label**: Custom set the `Volume Description Label` in the Inventory window.

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
**https://docs.tapetrack.com/master/preferences?rev=1783556583**

Last update: **2026/07/09 00:23**