


Set Volume Slot Manually

Prerequisites

- Target Repository must have an active Zone with vacant Slots available.
- Volume must be in a move to, or currently at, the Repository into which it is to be Slotted.

Setting Slot For Volumes

Double click the required Volume to open the Volume Properties window.



Open the Target Repository tab.

Edit Volume: 001564L6

Datasets

Attributes

VeriScore™

DR Strategies

Options

Catalog

Identity

Target Location

Current Location

Scanned Location

Notes

History

Volume Attributes

Customer-ID

US02

Los Angeles Data Center

Media-ID

LTO

LTO Cartridge

Volume-ID

001564L6


001564L6

Update Statistics

Save

Cancel

Help

If the Volume is located in another Repository and not moving to the Repository to be Slotted in, you will need to select the required Repository from the drop down list in the Virtual Location Repository field. Click Yes to open the Slot Allocation window.

Edit Volume: 001564L6

Datasets		Attributes		VeriScore™		DR Strategies		Options		Catalog	
Identity		Target Location		Current Location		Scanned Location		Notes		History	
Virtual Location Repository Library											
Physical Location Zone No-Alloc											
Slot 0											
Update Statistics When Date Monday, July 26, 2021 (0 days ago)											
Time 14:14:20											
UTC Offset 600 minutes											
Time at source Monday, July 26, 2021 - 14:14:20											
Time Zone AUS Eastern Standard Time											
From Machine Name 127.0.0.1 (GazillaByte)											
Details Connection Count 2,513											
First Connection Sunday, August 04, 2019 - 16:44:36											
Last Connection Monday, July 26, 2021 - 09:37:42											
Interface TapeTrack TapeMaster											
Operating System Windows											
As User-ID doco											
User Name doco											

Save Cancel Help

If the Volume is already in a move to, or located at, the Slotting Repository, under Virtual Location click in the Slot field and then click the ... button to open the Slot Allocation window.

Click on the required unallocated Slot and then click OK to assign the Volume to that slot.

Click Save on the Volume Properties window to save the Target Slot data.

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://docs.tapetrack.com/technote/set_slot_manually?rev=1627273846

Last update: **2025/01/21 22:07**

