


# Set Volume Slot Manually

## Prerequisites

- Target Repository must have an active Zone with vacant Slots available.
- Volume must be in a move to, or currently at, the Repository into which it is to be Slotted.

## Setting Slot For Volumes

Double click the required Volume to open the Volume Properties window.



Open the Target Repository tab.

Edit Volume: 001564L6

Datasets Attributes VeriScore™ DR Strategies Options Catalog

Identity Target Location Current Location Scanned Location Notes History

Volume Attributes

Customer-ID US02 Los Angeles Data Center

Media-ID LTO LTO Cartridge

Volume-ID 001564L6

001564L6

Update Statistics

Save Cancel Help

If the Volume is located in another Repository and not moving to the Repository to be Slotted in, you will need to select the required Repository from the drop down list in the Virtual Location Repository field to place it in a move status. Click Yes to open the Slot Allocation window.

Edit Volume: 001564L6

| Datasets | Attributes      | VeriScore™       | DR Strategies    | Options | Catalog |
|----------|-----------------|------------------|------------------|---------|---------|
| Identity | Target Location | Current Location | Scanned Location | Notes   | History |

|                   |                                    |
|-------------------|------------------------------------|
| Virtual Location  |                                    |
| Repository        | Library                            |
| Physical Location |                                    |
| Zone              | No-Alloc                           |
| Slot              | 0                                  |
| Update Statistics |                                    |
| When              |                                    |
| Date              | Monday, July 26, 2021 (0 days ago) |
| Time              | 14:14:20                           |
| UTC Offset        | 600 minutes                        |
| Time at source    | Monday, July 26, 2021 - 14:14:20   |
| Time Zone         | AUS Eastern Standard Time          |
| From              |                                    |
| Machine Name      | 127.0.0.1 (GazillaByte)            |
| Details           |                                    |
| Connection Count  | 2,513                              |
| First Connection  | Sunday, August 04, 2019 - 16:44:36 |
| Last Connection   | Monday, July 26, 2021 - 09:37:42   |
| Interface         | TapeTrack TapeMaster               |
| Operating System  | Windows                            |
| As                |                                    |
| User-ID           | doco                               |
| User Name         | doco                               |

Save Cancel Help

If the Volume is already in a move to, or located at, the Slotting Repository, under Virtual Location click in the Slot field and then click the ... button to open the Slot Allocation window.

Click on the required unallocated Slot and then click OK to assign the Volume to that slot.

Click Save on the Volume Properties window to save the Target Slot data.

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

[https://docs.tapetrack.com/technote/set\\_slot\\_manually?rev=1627293827](https://docs.tapetrack.com/technote/set_slot_manually?rev=1627293827)

Last update: **2025/01/21 22:07**

