TMSS10MoveLocation

TMSS10MoveLocation puts selected Volumes in a move from one Repository to another.

Synopsis

```
TMSS10MoveLocation [-C check if volume is assigned to a container] [-M move only if container moving] [-S logon string] [-T move only if assigned container target matches] [-V volume] [-X skip volumes assigned to a container] [-c configuration file] [-e exclude volumes already moving] [-f from repository] [-l apply move lock during move] [-t to repository]
```

Options

- `-C` Move Volume only when assigned Container is moving and matches move requirements.
- `-M` Move only if the assigned Container is moving (requires -C) (default = false).
- `-S` The Logon string argument sets the Server Logon Information.
- `-T` Move only if the assigned Container Target matches (requires -C) (default = false).
- `-V` Volume Filter which can be used to filter the traversal of Customer, Media, Volume, Repository and Flag values.
- `-X` Skip any volumes already assigned to a container.
- `-c` The config file argument specifies the path to the Batch Configuration File. The Batch Configuration File allows you to perform advanced traversal of Customer, Media and Volumes, perform advanced Barcode pre and post processing and route program output to syslogd.
- `-e` Exclude any Volumes that are already in a Move Status.
- `-f` Repository to Move Volumes from.
- `-l` Apply a move-lock to Volumes during move.
- `-t` Repository to move Volumes to.

If an argument value starts with the value `FI:`, the value for that attribute will be read from the file name specified immediately after it. For example, if a file named ACME_volumes has the content `ACME_*.*`, specifying `FI:/etc/ACME_volumes` will have the same effect as `-V ACME.*.*`. Using `FI:` to refer to a file for an attribute value works for all attributes.

If the pattern being matched starts with *LIST: then rather than matching the literal value, each record in the file specified as *LIST:filename will be tested. If one matches the match will succeed.

2025/01/21 22:08
include page

Technical Support

The TapeTrack Software is commercially supported by a full time help desk staff.

If you are experiencing problems or want some advice on how to configure or use the product please

see the Accessing Technical Support page.

Exit Statuses

1. **zero** Program has ended successfully.
2. **non-zero** Program has not ended successfully.

Environment

Files

stdout: Output Reports.
stderr: Diagnostic messages.
stdin: Program input.

Example

Command line syntax

Move all US02 LTO Volumes with a Barcode ending in 5L6.

```
TMSS10MoveLocation -S user:-password@server -V "US02.LTO.*5L6" -f "LIBR" -t
"OFFS"
```

Output

```
            System: TapeTrack
 Report Description: Volumes Moved
       Report Notes: From(LIBR) To(OFFS)
    Production Time: Monday, November 27, 2017 - 12:56:38 (AUS Eastern
Daylight Time)
       Report Width: 92 bytes

 Seq.   Barcode              From                To
Container
 ------ -------------------- ------------------- ------------------- -----
---------------
      1 US02.LTO.000015L6    Library             Offsite Vault
      2 US02.LTO.000035L6    Library             Offsite Vault
      3 US02.LTO.000065L6    Library             Offsite Vault
      4 US02.LTO.000075L6    Library             Offsite Vault
      5 US02.LTO.000085L6    Library             Offsite Vault
      6 US02.LTO.000095L6    Library             Offsite Vault
      7 US02.LTO.000105L6    Library             Offsite Vault
```

```
      8 US02.LTO.000115L6    Library              Offsite Vault
      9 US02.LTO.000125L6    Library              Offsite Vault
     10 US02.LTO.000135L6    Library              Offsite Vault
     11 US02.LTO.000145L6    Library              Offsite Vault
     12 US02.LTO.000155L6    Library              Offsite Vault
     13 US02.LTO.000165L6    Library              Offsite Vault
     14 US02.LTO.000175L6    Library              Offsite Vault
     15 US02.LTO.000185L6    Library              Offsite Vault
     16 US02.LTO.000195L6    Library              Offsite Vault
     17 US02.LTO.000205L6    Library              Offsite Vault
     18 US02.LTO.000215L6    Library              Offsite Vault
     19 US02.LTO.000225L6    Library              Offsite Vault
     20 US02.LTO.000235L6    Library              Offsite Vault
     21 US02.LTO.000245L6    Library              Offsite Vault
     22 US02.LTO.000255L6    Library              Offsite Vault
     23 US02.LTO.000265L6    Library              Offsite Vault
     24 US02.LTO.000275L6    Library              Offsite Vault
     25 US02.LTO.000285L6    Library              Offsite Vault
     26 US02.LTO.000295L6    Library              Offsite Vault
     27 US02.LTO.000305L6    Library              Offsite Vault
     28 US02.LTO.000315L6    Library              Offsite Vault
 ------ -------------------- -------------------- -------------------- -----
---------------
```

See Also

Command Line Utility Troubleshooting and Diagnosis

Changelog

Cannot load rss feed.

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/cli/tmss10movelocation

Last update: **2025/07/04 04:47**