Picking and Distribution List

A Picking and Distribution List is a report that lists tapes that are moving from one location to another.

The report is made up of four or more sections. Each section being tapes moving from a specific location (picking) and tapes moving to a specific location (distribution).

There will always be at least 4 reports because for there to be movement there must be at least two locations. In this instance, there will be a picking and distribution list for each of the two locations.

<sxh> WEDNESDAY , AUGUST DD, YYYY.222 Y O U R C O M P A N Y N A M E PAGE 1

```
                                                        PARM=PARMUPD=TEST
```

TMS REPORT-25 PICKING LIST FOR VAULT (LIBR) CARTRIDGE

VOLSER SLOT DATA SET NAME NEW NEW VOL EXPIRATION LBL CREATE CREATE CREATE PATT

```
      NUMBER                                                VAULT    SLOT   SEQ
DATE       TYPE   JOBNAME   DATE             TIME    USED
```

——

061000 ASM2.ARCH.MASTER DRA1 001 001 PERMANENT SL-36 ASM2ARCH YYYY/175 00:00:00 0002 061001 ASM2.BKUP.MASTER DRA1 002 001 PERMANENT SL-36 ASM2BKUP YYYY/175 00:00:00 0002 061004 ADMIN.PAYR.DYL.G0406V00 SAFE 001 001 CATALOG SL-36 ADMINPDY YYYY/196 00:00:00 0001 061005 ADMIN.PAYR.WLY.G0088V00 SAFE 002 001 CATALOG SL-36 ADMINPWY YYYY/197 00:00:00 0001 061006 ADMIN.PAYR.PAYR.DLY.G0405V00 SAFE 003 001 CATALOG SL-36 ADMINPDY YYYY/198 00:00:00 0001 061007 ADMIN.PAYR.DLYBKUP.G0406V00 SAFE 004 001 CATALOG SL-36 ADMINPDY YYYY/199 00:00:00 0001 061008 ADMIN.PAYR.DLYBKUP.G0405V00 SAFE 005 001 CATALOG SL-36 ADMINPDY YYYY/198 00:00:00 0001 061009 ADMIN.PAYR.MLY.G0045V00 SAFE 006 001 CATALOG SL-36 ADMINMY YYYY/211 00:00:00 0001

8 TAPES

8 TAPES

GRAND TOTAL

```
                8  TAPES
```

</sxh>

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/general/picking_and_distribution?rev=1524187552

Last update: **2025/01/21 22:07**