
Scan-Out

The TapeTrack Lite Scan-Out function allows you to place Volumes in a Move status from their Current Repository to a Target Repository.

When a Volume is put into a move status this only represents the request to move the Volume and a second step is required to confirm the movement of the Volume when it arrives at the Target Repository.

The Scan-Out process is used to record the Volumes have left the current location or Repository, adding an historical entry in the database to record the chain of custody of the scanned Volumes]. ===== Scan-Out Process ===== <note tip>The Scan-Out video is intended as a companion to the instructions. \\ Best results are obtained by reading the instructions and then viewing the implementation of the process via the video</note> {{lite:lite_scan_out.mp4?500}} ==== Selecting Scan-Out ==== Select ''Scan-Out'' from the **Task Menu** and click ''Next'' to continue. {{:desktop:lite_scan_out.png}} ==== Options ==== This will open the **Options** window. If required you can set the location for the log files to be written to, or leave the default. To change the default directory, click in the field to the right of the Log File Folder and click on the (...) button and select directory. Click ''Next'' to continue. {{:desktop:lite_scan_out_log.png}} ==== Customer Selection ==== Select the account or [[object:customer|Customer that you want to manage Volumes for by double-clicking the `Customer-ID` or left-clicking the `Customer-ID` and clicking `Next` at the bottom of the page.




Checking `Remember previously selected Customer` will retain the currently selected Customer for future Lite functions.

This can be removed at any time by unchecking `Remember previously selected Customer`

Scan-Out Location

In the **Scan-Out Location** window select a Repository to Scan-Out the Volumes from by double-clicking on the `Repository` or left-click to select `Repository` and click `Next` to proceed.




Scan-Out Container Location

If using Containers with unique identities, select from the displayed list the required Containers to assign the Volumes to. Select one Container by double-clicking or by left-clicking `Container ID` and clicking `Next`. To select multiple Containers control + left-click to select required choices. Containers can also be Scanned-Out by clicking the Open **Volume Scan-In** window by clicking on Scan-in Button which will launch the Desktop Scan Window and scan required Containers.

If Volumes have already been assigned to a Container via TapeMaster or Sync process, the correct Container/s will be pre-selected and shown in a grey background, or blue background when the window in clicked on.

If no Containers are needed simply click `Next`.




Scan-Out Volumes

The **Scan-Out Volumes** window will display the tapes eligible for Scanning-Out of the selected Customer and Repository.

This window also, by default, opens the **Scan-Out Volumes Input** window. Customer-ID and Media-ID values can be entered in the upper right Defaults panel to automatically add these values to the scanned Barcodes if scanning unqualified Barcodes. The field Edit in the Defaults panel can be used to add prefix or suffixes to the Volume-ID.

For example, setting the Customer-ID field to US01, Media-ID field to LTO and edit field to *L5 will change a Barcode of 123456 to US01.LTO.123456L5.



Notes:


- **A** The Scan-Out window shows the items that need to be scanned.
- **B** The Scanned Item tree shows the items that have been scanned and associated Containers. The Container shown in bold signifies the current Container allocation for scanned Volumes
- **C** The `Scanner button` allows you to reiterate the Scanner Window.
- **D** The `Scan-Out Log` option lists any errors in scanned Volumes .

Scan-Out the required Volumes using your preferred scanning method.

When finished Scanning-out Volumes click `Next` to continue. If you have not Scanned-Out the entire list a warning of Unscanned Items will be displayed.


If you wish to Scan-Out the rest of the Volumes click No to return to the Scan-Out Volumes window. If you wish to continue and leave the remaining Volumes unscanned (they can be scanned out at a future time) click `Yes` to continue.

If you wish to Scan-Out the rest of the remaining Volumes, click No to return to the Scan-Out list.



Scan-Out Container Update


From here you can set the next move date, add descriptions for the Container/s and whether to Scan-Out the Container/s as well as the Volumes .



This will bring up the **Complete** window, from here you can:

- Click `View Log File` to view the log file of the last completed process..
- Click `Print Log File` to save a PDF of the log file to print from your PDF viewer.
- Click `About this Software` to view product and support (email, phone & website) information.
- Click `Back` button to return to start menu and select another task.

- Click `Finish` button or X at the top right of the window to exit TapeTrack Lite.



2025/01/21 22:08

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/lite/function_scanning_out?rev=1613437192

Last update: **2025/01/21 22:07**