


# Built In Repositories

TapeMaster has 3 built in [Repositories](#), which are hidden by default.

To display the hidden [Repositories](#), navigate to the Options tab in the [Media](#) Type Properties Window and set Show Built In Repositories to **true**. The [Repositories](#) **Initial**, **Next** and **Home** will be displayed in the [Repository](#) window.



Built-In [Repositories](#) often do not exist as locations, but they use settings in the Options Tab of the Volume Properties Window to dictate movements.

## Built In Repository Functions

### Initial Repository

If No Selection is set in the Default Repository field in the Media Type Properties Window's Options Tab, newly added [Volumes](#) will be allocated to the Initial [Repositories](#).

Edit Media: LTO Cartridge

Identity

Volume-ID Building

Options


|                           |                |
|---------------------------|----------------|
| Hide Media Type           | False          |
| Internal                  | True           |
| Maximum Volumes           | 0              |
| Maximum Repositories      | 0              |
| Allowable Volume-IDs      |                |
| Default Media Type        | False          |
| Auto Simple Management    | False          |
| Auto Container            | False          |
| Stock Controlled          | False          |
| Auto Stock Selection      | False          |
| Relaxed Barcode Matching  | False          |
| No Move-back Warning      | False          |
| Lock Volumes              | False          |
| No HealthCheck            | False          |
| Show BuiltIn Repositories | True           |
| Remove barcode suffix     |                |
| Barcodes use Modulo43     | False          |
| Default Repository        | <No Selection> |

InventoryDR StrategiesData ClustersSimple ManagementUploaded FilesConsignments

Volumes

| ID              | Current Location   | Target Location | Flags     | Move Time  | Due in      | Container  | Next Move |
|-----------------|--------------------|-----------------|-----------|------------|-------------|------------|-----------|
| Enter text h... | Enter text here    | Enter text ...  | Enter ... | Enter t... | Enter t...  | Enter t... | Enter ... |
| 000001L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000002L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000003L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000004L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000005L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000006L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000007L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000008L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000009L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000010L5        | Initial Repository |                 | CnN       |            | Unspecified | Unassigned | Permanent |
| 000011L5        | Initial Repository |                 | Cn        |            | Unspecified | Unassigned | Permanent |
| 000012L5        | Initial Repository |                 | Cn        |            | Unspecified | Unassigned | Permanent |

Any other [Repositories](#) may be set as the default location for new [Volumes](#) by right-clicking the required [Repositories](#) and selecting Make Default Repository




## Home Repository

Dragging and dropping [Volumes](#) to the Home [Repository](#) places them into a move status to the [Repository](#) set as the Home Repository in the [Volume](#) Properties Window Options tab.


An example for using this function would be [Volumes](#) returning from offsite storage back on-site and needing to be stored in different racks ([repositories](#)). Having the required rack set for each [Volume](#) allows you to drag and drop all the [Volumes](#) on the Home [Repository](#) and letting TapeTrack sort which [repository](#) each of the [Volumes](#) belong in, saving you having to separate each group of [Volumes](#) for each [repository](#) manually.

A [Volume's](#) **Home Repository** can be set in the Volume Properties Window Options Tab.




or by right-clicking [Volumes](#) in the Volume List, then selecting [Special Operations](#), Modify, and Home

**Repository.** Selecting a range of **Volumes** allows you to assign multiple **Volumes** Home **Repository** in the one operation.



Select **Repository** from popup window drop-down box.



## Next Repository

Drag and dropping **Volumes** to the next **Repository** places them into a move status to the **Repository** set as the Next **Repository** in the **Volume** Properties Window Options tab.

From:  
<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
[https://docs.tapetrack.com/master/built\\_in\\_repositories?rev=1571267041](https://docs.tapetrack.com/master/built_in_repositories?rev=1571267041)

Last update: **2025/01/21 22:07**

