
# Generation Dispersement Table

The Generation Dispersement function displays a table of selected volumes based on their generation (ie. LTO 1, LTO 2) and current scratch (Z flag) status.


## View Generation Dispersement Table

Select volumes to be included in table by either right click in the volume window and `Select` → `All` or Ctrl+ A to select all, or range select by Shift+Click and/or Ctrl + click.

Right-click highlighted volumes and select `View` → `Generation Dispersement Table`.





Select from the popup whether you want the results to merge repositories and/or attributes as well as whether or not to ignore or include case sensitivity.




## No Merge In Table Results


Leaving all fields set to false will display the selected volume quantities in the **Generation Dispersement Table** separated by current repository, attribute value, scratch status and volume generation (both scratch and non scratch).




| Repository | Attribute | Total Z | Total !Z | Gen-0 Z | Gen-0 !Z | Gen-3 Z | Gen-3 !Z | Gen-5 Z | Gen-5 !Z |
|---|---|---|---|---|---|---|---|---|---|
| Enter text here | Enter text h | En... | En... | En... | En... | En... | En... | En... | En... |
| Library | Server 1 | 4 | 0 | 0 | 0 | 1 | 0 | 3 | |
| Library | Server 2 | 6 | 0 | 0 | 0 | 0 | 0 | 5 | |
| Offsite Vault | Server 2 | 1 | 0 | 0 | 0 | 0 | 0 | 0 | |
| Offsite Vault | Server 1 | 2 | 0 | 0 | 0 | 0 | 0 | 1 | |
| Scratch Volumes | Server 2 | 5 | 0 | 0 | 0 | 0 | 0 | 2 | |
| Scratch Volumes | Server 1 | 6 | 0 | 0 | 0 | 0 | 0 | 5 | |
| Total | | 24 | 0 | 0 | 0 | 1 | 0 | 16 | |

## Merge Repositories in Table Results

Setting **Merge Repositories** to True will display results in table the selected volume quantities in the **Generation Dispersement Table** separated by attribute value, scratch status and volume generation (both scratch and non scratch).




Generation Dispersement Table

| Repository | Attribute | Total Z | Total !Z | Gen-0 Z | Gen-... | Gen-3 Z | Gen-... | Gen-5 Z |
|---|---|---|---|---|---|---|---|---|
| Enter text here | Enter text here | E... | E... | E... | E... | E... | E... | E... |
| | Server 1 | 12 | 0 | 0 | 0 | 1 | 0 | 9 |
| | Server 2 | 12 | 0 | 0 | 0 | 0 | 0 | 7 |
| Total | | 24 | 0 | 0 | 0 | 1 | 0 | 16 |

## Merge Attributes In Table Results

Setting **Merge Attributes** to True will display the selected volume quantities in the **Generation Dispersement Table** separated by current repository, scratch status and volume generation.



Generation Dispersement Table

| Repository | Attribute | Total Z | Total !Z | Gen-0 Z | Gen-0 !Z | Gen-3 Z | Gen-3 !Z | Gen-5 Z | Gen-5 !Z | Ge |
|---|---|---|---|---|---|---|---|---|---|---|
| Enter text here | Ente... | En... | En... | En... | En... | En... | En... | En... | En... | En. |
| Library | | 10 | 0 | 0 | 0 | 1 | 0 | 8 | 0 | |
| Offsite Vault | | 3 | 0 | 0 | 0 | 0 | 0 | 1 | 0 | |
| Scratch Volumes | | 11 | 0 | 0 | 0 | 0 | 0 | 7 | 0 | |
| Total | | 24 | 0 | 0 | 0 | 1 | 0 | 16 | 0 | |

## Merge Repositories And Attributes In Table Results

Setting **Merge Repositories** and **Merge Attributes** to True will display the selected volume quantities in the **Generation Dispersement Table** separated by scratch status and volume generation.

Generation Dispersement Table

| Repository | Attribute | Total Z | Total !Z | Gen-0 Z | Gen-... | Gen-3 Z | Gen-... | Gen-5 Z |
|---|---|---|---|---|---|---|---|---|
| Enter text here | Enter text here | E... | E... | E... | E... | E... | E... | E... |
| | | 24 | 0 | 0 | 0 | 1 | 0 | 16 |
| Total | | 24 | 0 | 0 | 0 | 1 | 0 | 16 |

## Case Insensitive In Table Results


Case Inensitive allows the option of grouping or separating attribute values based on being identical except for case.

Setting **Case Insensitive** to `False` will treat Server 1 and server 1 as separate or individual entries.

Generation Dispersement Table

| Repository | Attribute | Total Z | Total !Z | Gen-0 Z | Gen-... | Gen-3 Z | Gen-... | Gen-5 Z |
|---|---|---|---|---|---|---|---|---|
| Enter text here | Enter text here | E... | E... | E... | E... | E... | E... | E... |
| Library | Server 1 | 3 | 0 | 0 | 0 | 0 | 0 | 3 |
| Library | Server 2 | 6 | 0 | 0 | 0 | 0 | 0 | 5 |
| Library | server 1 | 1 | 0 | 0 | 0 | 1 | 0 | 0 |
| Offsite Vault | Server 1 | 2 | 0 | 0 | 0 | 0 | 0 | 1 |
| Offsite Vault | Server 2 | 1 | 0 | 0 | 0 | 0 | 0 | 0 |
| Scratch Volumes | Server 2 | 4 | 0 | 0 | 0 | 0 | 0 | 1 |
| Scratch Volumes | Server 1 | 6 | 0 | 0 | 0 | 0 | 0 | 5 |
| Scratch Volumes | server 2 | 1 | 0 | 0 | 0 | 0 | 0 | 1 |
| Total | | 24 | 0 | 0 | 0 | 1 | 0 | 16 |

Setting **Case Insensitive** to `True` will treat Server 1 and server 1 as the same entry.


Generation Dispersement Table

| Repository | Attribute | Total Z | Total !Z | Gen-0 Z | Gen-... | Gen-3 Z | Gen-... | Gen-5 Z |
|---|---|---|---|---|---|---|---|---|
| Enter text here | Enter text here | E... | E... | E... | E... | E... | E... | E... |
| Library | Server 2 | 6 | 0 | 0 | 0 | 0 | 0 | 5 |
| Library | server 1 | 4 | 0 | 0 | 0 | 1 | 0 | 3 |
| Offsite Vault | Server 1 | 2 | 0 | 0 | 0 | 0 | 0 | 1 |
| Offsite Vault | Server 2 | 1 | 0 | 0 | 0 | 0 | 0 | 0 |
| Scratch Volumes | Server 1 | 6 | 0 | 0 | 0 | 0 | 0 | 5 |
| Scratch Volumes | server 2 | 5 | 0 | 0 | 0 | 0 | 0 | 2 |
| Total | | 24 | 0 | 0 | 0 | 1 | 0 | 16 |

Close the report by clicking the X at the top right corner.

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
**https://docs.tapetrack.com/master/generation_dispersement?rev=1553565552**

Last update: **2025/01/21 22:07**