

Preferences

The Preferences window, File → Preferences, sets basic customization for TapeMaster such as sounds, hidden objects, etc.



Options

- **Disable sounds:** If set to True, sounds in TapeMaster will be muted.
- **Case Insensitive Filters:** Case is ignored when matching strings against filters.
- **Show hidden Customers:** If set to True, the Customer Tree will display Customers that have the Hide Customer option in the Customer Properties Window set to True.
- **Show hidden Media:** If set to True, the Customer Tree will display Media Types that have the Hide Media Type option in the Options Tab of the Media Type Properties Window set to True.
- **Show hidden Volumes:** If set to True, the Volume List will display Volumes that have the Hide Volume option in the Options Tab of the Volume Properties Window set to True.
- **Parent/Child:** If set to False, the Customer Tree will not display Customers with a Parent Customer set in the Customer Properties Window nested under their Parent Customer.
- **Anonymous Customers:** If set to True, Customer Descriptions in the Customer Tree will not display.

- **Enable Consignment Tab:** If set to True, the Consignments tab will appear as an Administration Tab.
- **Repository-ID filters:** If set to True, [Volumes](#) in the [Volume](#) List can be filtered by the Repository-ID instead of the Repository Description.
- **Disable Volume List inline edit:** If set to True, inline editing in [Volume](#) List will be disabled. (Requires restart)
- **Volume List Above Repository List:** Reorganize [Volume](#) and Repository windows in the GUI. True = [Volumes](#) displayed above Repositories. False = Repositories above [Volumes](#).
- **Location Auto Swap:** If set to True, will display the [Volume](#) slot location instead of slot number if inventory quantity is under the Location Auto Swap Max value.
- **Location Auto Swap Max** sets the maximum number of [Volumes](#) to enable the Location Auto Swap function. This field only displays when Location Auto Swap is set to True.
- **Show Volume Refresh Clock:** If set to True a counter will display the time in seconds from the last time the Volume window was refreshed. Changes will take effect on restart of TapeMaster.
- **Show Volume Health Score:** Display the [Library Health Score](#) in the Volume Properties window.
- **Volume Description Label:** Custom set the [Volume](#) Description Label in the Inventory window.

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://docs.tapetrack.com/master/preferences?rev=1783387410>

Last update: **2026/07/07 01:23**

