

Adding and Updating User Information

To be able to login to a TapeTrack Framework Server, you must have a [User-ID](#) and password.

This section describes how to create a new User-ID and set Attributes for that User-ID.

Group/User Administration

From the main menu select Administration → Group/User Administration.




If the menu option **Administration** is greyed out and inaccessible, you do not have sufficient privileges (tapemaster rights) to add Users

The screenshot displays the TapeTrack TapeMaster™ (GazillaByte) application window. The main menu includes File, Administration, Favorites, Tools, View, and Help. A Customer Filter is present. The left sidebar shows a tree view of the production environment, including US00 - United State, US01 - New York, US02 - Los Angel, CONT - Conta, LTO - LTO Car, and US03 - North Car. The main area shows the 'Volumes' section for the 'Los Angeles Data Center' and 'LTO Cartridge'. A table lists various volumes with columns for ID, Current Location, Target Location, Next Move, and Description. The bottom status bar indicates 'Total Items: 1,585', 'Total Selected: 1', and 'First Selection: 16'. The 'Repositories' section at the bottom shows icons for Gemtrac, Library, Transport, and Offsite Vault. The connection status at the bottom right states 'Connection 127.0.0.1 uses AES 256 bit encryption'.

ID	Current Location	Target Location	Next Move	Description
000000L6	Offsite Vault	Library	Permanent	
000001L6	Library	Offsite Vault	Permanent	
000002L6	Library	Offsite Vault	Permanent	
000003L6	Library		Wednesday, May ...	Monthly
000004L6	Library		Permanent	
000005L6	Library	Offsite Vault	Friday, June 18, 20...	Weekly 1
000006L6	Library	Offsite Vault	Friday, June 18, 20...	Weekly 1
000007L6	Library	Offsite Vault	Friday, August 20,...	Monthly
000008L6	Library		Permanent	
000009L6	Library		Permanent	
000010L6	Library		Permanent	
000011L6	Offsite Vault		Monday, May 17, ...	DB Backup
000012L6	Library	Transport	Permanent	
000013L6	Offsite Vault		Permanent	
000014L6	Offsite Vault		Permanent	
000015L6	Offsite Vault		Permanent	
000016L6	Offsite Vault	Library	Permanent	

To add a new User, right-click in the white space on the User Administration screen and select Add.



To update an existing User, double-click on that User or right-click and select Properties.

The Add New User window will display three tabs:

- [Identity](#)
- [IP Ranges](#)
- [Access](#)

Identity

The screenshot shows the 'Add New User' dialog box with the 'Identity' tab active. The dialog has three tabs: 'Identity', 'IP Ranges', and 'Access'. The 'Identity' tab contains several sections:

- Identity**: Fields for 'ID' and 'Name'.
- Group**: Field for 'ID'.
- Options**: A list of options with checkboxes: 'Administrative rights' (False), 'Scan-In Only' (False), 'Disabled' (False), 'No Scanner' (False), 'No Time-Out' (False), 'tapemaster rights' (False), 'Allow access inheritance' (False), 'Certify' (False), 'AD Domain' (False), 'Require AD Group' (False).
- Client Access**: A list of options with checkboxes: 'TapeMaster' (True), 'Lite' (True), 'Checkpoint' (False), 'Sync' (True).
- Details**: Fields for 'Email Address' and 'Description'.
- Defaults**: Field for 'Customer-ID' with a dropdown menu showing '<No Selection>'.

At the bottom of the dialog are three buttons: 'Save', 'Cancel', and 'Help'.

The Identity tab provides fields to update the:

- **Identity**
 - **User-ID**: The User-ID will be the user name that the user uses to login to TapeTrack products.
 - **Name**: The name is the User's desired display name.
- **Group**
 - **Group-ID**: Select group to assign user to from the drop-down list or [add new group](#).
 - **Role**: Hierarchical role of the User.
- **Options**
 - **Administrative rights**: When set to True the User will have Administration Rights with Server Administrator privileges or the ability to Add/Delete Customers and Media Types.
 - **Scan-In Only**: When set to True the User will only be able to Scan tapes into the system.
 - **Disabled**: When set to True the User's access will be in a disabled status, so that they are not able to access any TapeTrack products. This does not delete the User.
 - **No Scanner**: When set to True the Barcode Scanning Window will provide an auto-

complete drop-down.

- **No Time-Out:** By default, all User's are logged out of TapeMaster after ten minutes of inactivity. Setting this to True, the selected User will not time out.
- **tapemaster rights:** When set to True, it allows the User to gain the same administrative rights as the tapemaster superuser account. Only the User-ID tapemaster can add tapemaster rights to another user.
- **Allow access inheritance:** Allows User to inherit another User's access rights using variable [TMSSUSERINHERIT](#) with [Command Line Utility](#) Programs
- **Certify:** Assigns the ability to [generate certificates](#).
- **AD Domain:** This is required if the User logs on to TapeTrack with their Active Directory Username and Password.
- **Require AD Group:** When set to True, the User must use their [Active Directory](#) credentials to logon.
- **Client Access**
 - **TapeMaster:** Authorizes User-ID access to TapeMaster
 - **Lite:** Authorizes User-ID access to Lite
 - **Checkpoint:** Authorizes User-ID access to Checkpoint
 - **Sync:** Authorizes User-ID access to Sync software.
- **Details**
 - **Email Address:** Allows inclusion of user email, which may be used instead of username to log into TapeTrack directly (ie not using Active Directory)
 - **Description:** Add description to User-ID.
- **Defaults**
 - **Customer-ID:** Sets Customer-ID for User in Scan-In window. Once Customer-ID is set, Media-ID field will be displayed.
 - **Media-ID:** Sets Media-ID for User in Scan-In window.




If using windows Active Domain to log into TapeTrack, the username must match your AD username

IP Ranges

The IP Ranges tab sets restrictions on which IP addresses a User can access the TapeTrack Server from.

If setting IP's, ensure Users have a static IP address so they are not denied access if trying to access from a dynamic address such as using a remote or home connection.



To add or delete, right-click the window and select from the menu.

Global Access (0.0.0.0) will allow access from any IP, this value will need to be removed if added a restricted IP list as all values in the list are valid.

Access

The Access tab sets permissions for which Customers the selected User can access and how that User can interact with Volumes in the selected Customer.

Add New User

Identity IP Ranges Access

Customer-ID	Access
Read	False
Write	False
Alter	False
Catalog	False

Add

There are no items to display in this list.

Access Prediction

Customer	Description	Access
There are no items to display in this list.		

Total Items 0

Save Cancel Help

- **Customer-ID:** Enter the Customer-ID for the Customer that the User should have access to.
 - US01 will give access to US01 only
 - US* will give access to all customers starting with US
 - * will give access to all customers
- **Read:** Allows the User to view but not update Volumes in the above Customer. Must be enabled for the User to be able to view Volumes in the selected Customer-ID.
- **Write:** Allows the User to perform basic operations for Volumes to the selected Customer.
- **Alter:** Allows the User to Add and Delete Media and Volumes to the selected Customer.
- **Catalog:** Allows User to access Catalog information on the selected Customer.

For each Customer access, click Add to commit the data. Predicted access rights will then be displayed in the lower window.

Once all data has been entered, click Save to create User.

[Troubleshooting: Add user errors](#)

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://docs.tapetrack.com/master/user?rev=1617055933>

Last update: **2025/01/21 22:07**

