Printing Unqualified Barcode Labels


Printing Unqualified Barcodes with TapeTrack Barcode Printer is accomplished by loading the Barcodes via a text file.

Creating The Barcode Text File

Information in the text file has the format of `barcode:text_under_barcode`, one barcode per line.

The Barcode Text File can be created several different ways, which method is best used depends on the quantity of Barcode labels required.

If only a couple of labels are required, the easiest method is to use a text editor like Notepad to manually type the labels required.




If a large number of Barcode Labels using Excel to create the required values for the text file.

- Selecting the Volumes in TapeMaster and copying values to your clipboard by right clicking the highlighted Volumes and selecting `Edit` → `Copy` → `Unqualified Volumes`.
- Open Excel and paste Volume-ID's into an Excel spreadsheet column A
- Add `;` to column B and drag cell to auto fill the cells next to column A values
- Use cell formulas to concatenate the cell values to one column using formula `=CONCAT(A1,B1,A1)` to create the barcode;barcode format.
- Copy the concatenated column and paste into a Notepad file, saving under a known name and location.

Opening The Barcode Printer

Open the Barcode Printer via the Windows Start Menu at `TapeTrack` → `Barcode Printer`




Alternatively, navigate in File Explorer to the TapeTrack TapeMaster installation directory and run the executable `TMSSBarcodePrinter.exe`.

Loading Barcodes From Text File

From the Main Menu select `File` → `Open`

Navigate to and select the Barcode Text File. Click `Open' to load the file.`



===== Editing Print Layout ===== Use the left window pane on the Barcode Printer to edit the print layout options to suit your requirements. * Across: Number of barcodes to print across the page. * Down: The number of barcodes to print down the page. * Margins: Margins to be placed around the barcodes * Left: Left margin padding * Right: Right margin padding * Top: Top margin padding * Bottom: Bottom margin padding * Appearence: * Separator Box: Adds a grey border around each Barcode to aid in separating individual Barcodes. * Preview Margins: Adds a preview of print boundaries to aid in confirming Barcode will print within a specified area. * QR Code: Adds a QR code to the Barcode label. * Include Human Readable: Adds text representation of Barcode to make it readable by Humans. * Font'': Sets font for Human Readable content, does not alter Barcode.

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/print_barcodes/unqualified?rev=1617337969

Last update: **2025/01/21 22:07**