Printing Unqualified Barcode Labels


Printing Unqualified Barcodes with TapeTrack Barcode Printer is accomplished by loading the Barcodes via a text file.

Creating The Barcode Text File

Information in the text file has the format of `barcode:text_under_barcode`, one barcode per line.

The Barcode Text File can be created several different ways, which method is best used depends on the quantity of Barcode labels required.

If only a couple of labels are required, the easiest method is to use a text editor like Notepad to manually type the labels required.




If a large number of Barcode Labels using Excel to create the required values for the text file.

- Selecting the Volumes in TapeMaster and copying values to your clipboard by right clicking the highlighted Volumes and selecting `Edit` → `Copy` → `Unqualified Volumes`.
- Open Excel and paste Volume-ID's into an Excel spreadsheet column A
- Add `;` to column B and drag cell to auto fill the cells next to column A values
- Use cell formulas to concatenate the cell values to one column using formula `=CONCAT(A1,B1,A1)` to create the barcode;barcode format.
- Copy the concatenated column and paste into a Notepad file, saving under a known name and location.

Opening The Barcode Printer

Open the Barcode Printer via the Windows Start Menu at `TapeTrack` → `Barcode Printer`




Alternatively, navigate in File Explorer to the TapeTrack TapeMaster installation directory and run the executable `TMSSBarcodePrinter.exe`.

Loading Barcodes From Text File

From the Main Menu select `File` → `Open`

Navigate to and select the Barcode Text File. Click `Open` to load the file.



Editing Print Layout

Use the left window pane on the Barcode Printer to edit the print layout options to suit your requirements.

- `Across`: Number of barcodes to print across the page.
- `Down`: The number of barcodes to print down the page.
- `Margins`: Margins to be placed around the barcodes
    - `Left`: Left margin padding
    - `Right`: Right margin padding
    - `Top`: Top margin padding
    - `Bottom`: Bottom margin padding
- `Appearance`:
    - `Separator Box`: Adds a grey border around each Barcode to aid in separating individual Barcodes when manually cutting them out.
    - `Preview Margins`: Adds a preview of print boundaries to aid in confirming Barcode will

print within a specified area.
- `QR Code`: Adds a QR code to the Barcode label.
- `Include Human Readable`: Adds text representation of Barcode to make it readable by Humans.
- `Font`: Sets font for Human Readable content, does not alter Barcode.

From:
https://docs.tapetrack.com/ - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/print_barcodes/unqualified?rev=1617338059

Last update: **2025/01/21 22:07**