


Remove Slot Level Display In TapeMaster

Modify the TapeMaster Configuration File

Locate the TapeMaster Configuration file (default location C:\Program Files\TapeTrack\TapeTrack TapeMaster\TMSSMaster.cfg) and open with Notepad or other plain text editor.

Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    /*
    variables = {
        TMSSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```

Remove comment tags `/*` & `*/` from above and below variables.

Change the line of code
TMSSLEVELNAMES = "A,B,C";
to
TMSSNOLEVELSLOT = "true";

```
TMSSMaster.cfg - Notepad
File Edit Format View Help

options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    variables = {
        TMSSNOLEVELSLOT = "true";
    };

    showparent = true;
};

defaults = {
```

and save file.



Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file or other file extension.

To check the modification was successful:

Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below.

Before modification - TapeMaster displaying Zone, shelf and slot.

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
Enter text here	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6.1]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10.10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10.10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

After modification - TapeMaster displaying Zone and shelf only.

Inventory								
DR Strategies								
Data Clusters								
Simple Management								
Uploaded Files								
Consignments								
Volumes								
ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Mo	
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6]		CNO		Unspecified	Unassigned	Perman	
000002L5	Rack_01 [10]		CGNO		Unspecified	Unassigned	Perman	
000003L5	Rack_03 [10]		CNO		Unspecified	Unassigned	Perman	
000004L5	Library		CnN		Unspecified	Unassigned	Perman	
000005L5	Library		CnN		Unspecified	Unassigned	Perman	
000006L5	Library		CEnN		Unspecified	Unassigned	Perman	



If when opening TapeTrack TapeMaster you receive an error - **Failed to read configuration file (TMSSMaster.cfg): Line() - Syntax error** check the configuration file that you have used plain ASCII quotes (" ") and not rich text quotes (" ") and that the replaced text is correct.

[technote](#), [config](#), [slotting](#), [tapemaster slot](#), [update-doco](#)

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://rtfm.tapetrack.com/technote/config_file_tapemaster/remove_slot

Last update: **2026/07/15 01:59**

