


TapeMaster Configuration File

To modify TapeMaster, open TMSSMaster.cfg in a plain text editor such as Notepad.

TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

Remove Slot Level Display

Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    /*
    variables = {
        TMSSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```

Remove comment tags `/*` & `*/` from above and below variables.

Change the line of code

TMSSLEVELNAMES = "A,B,C";

to

TMSSNOLEVELSLOT = "true";

```
TMSSMaster.cfg - Notepad
File Edit Format View Help

options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    variables = {
        TMSSNOLEVELSLOT = "true";
    };

    showparent = true;
};

defaults = {
```

and save file



Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg or TMSSLite.cfg and not as a text file or other file extension.

To check the modification was successful:

Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below.

Before modification - TapeMaster displaying Zone, shelf and slot.

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6.1]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10.10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10.10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

After modification - TapeMaster displaying Zone and shelf only.

InventoryDR StrategiesData ClustersSimple ManagementUploaded FilesConsignments

Volumes

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Mo
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6]		CNO		Unspecified	Unassigned	Perman
000002L5	Rack_01 [10]		CGNO		Unspecified	Unassigned	Perman
000003L5	Rack_03 [10]		CNO		Unspecified	Unassigned	Perman
000004L5	Library		CnN		Unspecified	Unassigned	Perman
000005L5	Library		CnN		Unspecified	Unassigned	Perman
000006L5	Library		CEnN		Unspecified	Unassigned	Perman

From:

<https://docs.tapetrack.com/> - TapeTrack Documentation

Permanent link:

https://docs.tapetrack.com/technote/config_file_tapemaster?rev=1530234997

Last update:

2025/01/21 22:07

