

# Technical Note: Slot Numbering

When a Volume has a slot in TapeTrack, the slot is represented by both a [Virtual Slot](#) and [Physical Slot](#).

When displaying Physical Slot, the slot will either be displayed as a slot, or a level and a slot (when the Zone the slot belongs to has defined slots per level).


It is possible to change the way a Physical Slot is displayed in TapeTrack Desktop and TapeTrack Batch programs by defining changes in the [Configuration File](#).

## Changing Physical Slot Representation

### Masking the Slot

The display in TapeMaster and Lite can be modified to mask the slot number of the volumes, displaying zone and shelf only. This can be useful storing tapes in drawers with a limited number of slots, allowing librarians to slot the volumes quickly in a zones shelf location without needing to adhere to a slot number.

No Slot Masking - TapeMaster displaying Zone, shelf and slot (in the format **Zone\_ID [shelf\_number.slot\_number]**).



| ID       | Current Location | Target Location | Flags | Move Time | Due in      | Container  | Next Move |
|----------|------------------|-----------------|-------|-----------|-------------|------------|-----------|
| 000001L5 | Rack_01 [6.1]    |                 | CNO   |           | Unspecified | Unassigned | Permanent |
| 000002L5 | Rack_01 [10.10]  |                 | CGNO  |           | Unspecified | Unassigned | Permanent |
| 000003L5 | Rack_03 [10.10]  |                 | CNO   |           | Unspecified | Unassigned | Permanent |
| 000004L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Permanent |
| 000005L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Permanent |
| 000006L5 | Library          |                 | CEnN  |           | Unspecified | Unassigned | Permanent |

Slot Masking - TapeMaster displaying Zone and shelf only (in the format **Zone\_ID [shelf\_number]**).

| ID       | Current Location | Target Location | Flags | Move Time | Due in      | Container  | Next Move |
|----------|------------------|-----------------|-------|-----------|-------------|------------|-----------|
| 000001L5 | Rack_01 [6]      |                 | CNO   |           | Unspecified | Unassigned | Permanent |
| 000002L5 | Rack_01 [10]     |                 | CGNO  |           | Unspecified | Unassigned | Permanent |
| 000003L5 | Rack_03 [10]     |                 | CNO   |           | Unspecified | Unassigned | Permanent |
| 000004L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Permanent |
| 000005L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Permanent |
| 000006L5 | Library          |                 | CEnN  |           | Unspecified | Unassigned | Permanent |

Further information and instructions on [masking slots can be found here](#)

## Changing The Level

When creating (or editing) a storage zone for volumes you have the ability to specify not only the number of slots but the number of slots per level or shelf. This enables TapeTrack to display the location of a volume by zone, shelf and slot number.

If you prefer shelf levels to be displayed alphabetically, or any other string values, this can be achieved via the desktop software configuration file.

## Setting Shelf Name Values

Open the configuration file, found in the desktop installation directory (eg TapeMaster default installation directory TapeTrack/Tapemaster/TMSSMaster.cfg, Lite default installation TapeTrack/Tapemaster/TMSSLite.cfg) in a text editor such as Notepad.

- Uncomment (remove /\* above and \*/ below) the code block `variables = { TMSSLEVELNAMES="A,B,C"; };`
- Set the shelf names as required, default is level 1 = A, level 2 = B and level 3 = C.
- Add any extra shelf names if required, for example if you have 10 shelves  
`TMSSLEVELNAMES="A,B,C,D,E,F,G,H,I,J";`
- Save file, ensuring it is saved with the extension .cfg and not .txt
- Restart your desktop software and check the change is effected correctly

## Example

TapeTrack TapeMaster display with zone set to 10 slots per shelf. Display for volume 000001L5 shows in Zone Rack\_01, shelf 6, slot 1 (in the format **Zone\_ID [shelf\_number.slot\_number]**). The default display mode shows shelf allocation numerically.

| Inventory DR Strategies Data Clusters Simple Management Uploaded Files Consignments |                  |                 |           |            |             |            |            |           |
|-------------------------------------------------------------------------------------|------------------|-----------------|-----------|------------|-------------|------------|------------|-----------|
| Volumes                                                                             |                  |                 |           |            |             |            |            |           |
| ID                                                                                  | Current Location | Target Location | Flags     | Move Time  | Due in      | Container  | Next Move  |           |
| Enter text h                                                                        | Enter text h     | Enter text he   | Enter ... | Enter t... | Enter t...  | Enter t... | Enter t... | Enter ... |
| 000001L5                                                                            | GT1 [1.1]        |                 | CNO       |            | Unspecified | Unassigned | Permanent  |           |
| 000002L5                                                                            | GT1 [1.2]        |                 | CGNO      |            | Unspecified | Unassigned | Permanent  |           |
| 000003L5                                                                            | GT1 [1.3]        |                 | CNO       |            | Unspecified | Unassigned | Permanent  |           |
| 000004L5                                                                            | GT1 [1.5]        |                 | CNO       |            | Unspecified | Unassigned | Permanent  |           |
| 000005L5                                                                            | Library          | Offsite Vault   | CMnN      | H23:12:17  | Unspecified | Unassigned | Permanent  |           |
| 000006L5                                                                            | Library          | Offsite Vault   | CEMnN     | H23:12:17  | Unspecified | Unassigned | Permanent  |           |

After alteration to the TMSMaster.cfg to set TMSLEVELNAMES="A,B,C", TapeMaster displays the shelf levels alphabetically, exchanging 1 for A, 2 for B etc.

Display for volume 000001L5 shows in Zone Rack\_01, shelf A, slot 1 (in the format **Zone\_ID [shelf\_number.slot\_number]**).

| Inventory DR Strategies Data Clusters Simple Management Uploaded Files Consignments |                  |                 |           |            |             |            |            |           |
|-------------------------------------------------------------------------------------|------------------|-----------------|-----------|------------|-------------|------------|------------|-----------|
| Volumes                                                                             |                  |                 |           |            |             |            |            |           |
| ID                                                                                  | Current Location | Target Location | Flags     | Move Time  | Due in      | Container  | Next Move  |           |
| Enter text h                                                                        | Enter text h     | Enter text he   | Enter ... | Enter t... | Enter t...  | Enter t... | Enter t... | Enter ... |
| 000001L5                                                                            | GT1 [A.1]        |                 | CNO       |            | Unspecified | Unassigned | Permanent  |           |
| 000002L5                                                                            | GT1 [A.2]        |                 | CGNO      |            | Unspecified | Unassigned | Permanent  |           |
| 000003L5                                                                            | GT1 [A.3]        |                 | CNO       |            | Unspecified | Unassigned | Permanent  |           |
| 000004L5                                                                            | GT1 [A.5]        |                 | CNO       |            | Unspecified | Unassigned | Permanent  |           |
| 000005L5                                                                            | Library          | Offsite Vault   | CMnN      | H23:03:17  | Unspecified | Unassigned | Permanent  |           |
| 000006L5                                                                            | Library          | Offsite Vault   | CEMnN     | H23:03:17  | Unspecified | Unassigned | Permanent  |           |

From:

<https://docs.tapetrack.com/> - TapeTrack Documentation

Permanent link:

[https://docs.tapetrack.com/technote/slot\\_numbering?rev=1534207841](https://docs.tapetrack.com/technote/slot_numbering?rev=1534207841)

Last update:

2025/01/21 22:07

