


Location Auto Swap

The **Location Auto Swap** allows you to display the zone, draw and slot number (absolute location) rather than the default slot number (relative location) for each of the slotted **volumes** in the inventory window.


The default settings display slot numbers for each slotted volume.

Selecting a **volume** and hitting the backspace key will change the display for that volume to zone, drawer and slot.



ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next M
Enter text h...	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter
000001L3	GEMTRAC1 [1.1]		CNOt		Unspecified	Unassigned	Perma
000002L5	Offsite Vault [000004]		CDGNOt		Unspecified	Unassigned	Friday
000003L5	Offsite Vault [000003]		CNOtZ		Unspecified	Unassigned	Perma
000004L6	Offsite Vault [000007]		CNOtZ		Unspecified	Unassigned	Perma
000005L6	Offsite Vault [000009]		CNOtZ		Unspecified	Unassigned	Perma
000006L6	Offsite Vault [000013]		CNOt		Unspecified	Unassigned	Perma
000007L6	Offsite Vault [000016]		CNOt		Unspecified	Unassigned	Perma
000008L6	Offsite Vault [000022]		CNOt		Unspecified	Unassigned	Perma
000009L6	Offsite Vault [000030]		CDNOt		Unspecified	Unassigned	Saturd

Enabling the **Location Auto Swap** in the main preference's **Options** window (File → Preferences) and setting the **Location Auto Swap Max** number above the current inventory count (eg if you have 10,000 set the value higher to 20,000) will set the display to zone, draw and slot number as the default setting.



Options	
Disable sounds	True
Show hidden Customers	True
Show hidden Media	True
Show hidden Volumes	True
Parent/Child	False
Anonymous Customers	False
Enable Consignment Tab	True
Repository-ID filters	True
Disable Volume List inline edit	False
Location Auto Swap	True
Location Auto Swap Max	100

Once the **Location Auto Swap Max** has been enabled and saved, pressing F5 in the inventory window will update the display.

Selecting a **volume** and hitting the backspace key will change the display for that volume to slot number.

InventoryDR StrategiesData ClustersSimple ManagementUploaded FilesConsignments

Volumes

ID	Current Location	Target L...	Flags	Move Time	Due in	Container	Next Mo...
Enter text h...	Enter text here	Enter ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter text
000001L3	Offsite Vault [000001]		CNOt		Unspecified	Unassigned	Permane...
000002L5	GEMTRAC1 [1.4]		CDGNOt		Unspecified	Unassigned	Friday, A...
000003L5	GEMTRAC1 [1.3]		CNOtZ		Unspecified	Unassigned	Permane...
000004L6	GEMTRAC1 [1.7]		CNOtZ		Unspecified	Unassigned	Permane...
000005L6	GEMTRAC1 [1.9]		CNOtZ		Unspecified	Unassigned	Permane...
000006L6	GEMTRAC1 [1.13]		CNOt		Unspecified	Unassigned	Permane...
000007L6	GEMTRAC1 [1.16]		CNOt		Unspecified	Unassigned	Permane...
000008L6	GEMTRAC1 [1.22]		CNOt		Unspecified	Unassigned	Permane...
000009L6	GEMTRAC1 [1.30]		CDNOt		Unspecified	Unassigned	Saturday...



If the **Volume** count exceeds the maximum set in the **Location Auto Swap Max** field, the display will revert to the original default setting of slot number.

See Also

[TapeMaster Preferences](#)

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://docs.tapetrack.com/master/location_swap

Last update:

2026/07/21 01:39

