

Volume Target Location

When a [Volume](#) is placed in a move from its' Current Location to another Location, that other Location is a Target Location.

Once the [Volume](#) is confirmed at the Target Location, the [Volume's](#) Current Location is updated to match the Target Location, removing the [Volume's](#) Move (M) [Flag](#) and Move Status.

If [Slotting](#) is enabled the Target Location will, when a [Slot](#) is assigned, including the [Slot](#) Allocation details.

The screenshot shows the 'Edit Volume: 000013L6' window with the 'Target Location' tab selected. The window has a toolbar with icons for Datasets, Attributes, VeriScore™, DR Strategies, Options, and Catalog. Below the toolbar are tabs for Identity, Target Location, Current Location, Scanned Location, Notes, and History. The main content area is divided into several expandable sections:

- Virtual Location**
 - Repository: Offsite Vault
 - Slot: 282
- Physical Location**
 - Zone: Rack C
 - Slot: 9.2
- Update Statistics**
 - When**
 - Date: Monday, April 05, 2021 (63 days ago)
 - Time: 15:25:09
 - UTC Offset: 600 minutes
 - Time at source: Monday, April 05, 2021 - 15:25:09
 - Time Zone: AUS Eastern Standard Time
 - From**
 - Machine Name: 127.0.0.1 (GazillaByte)
 - Details**
 - Connection Count: 2,134
 - First Connection: Sunday, August 04, 2019 - 16:44:36
 - Last Connection: Tuesday, June 08, 2021 - 09:29:19
 - Interface: TMSS10SlotAllocation
 - Operating System: Windows
 - As**
 - User-ID: doco
 - User Name: doco

At the bottom right of the window are buttons for 'Save', 'Cancel', and 'Help'.

The Virtual location panel displays:

- Target [Repository](#).
- [Slot](#) Number allocated (if [Slotting](#) is enabled and [Volume](#) is allocated to a [Slot](#)).

If [Slotting](#) is not enabled, or no [Zones](#) mapped to the [Repository](#), [Slot](#) number will display as zero.

The Physical Location displays:

- The [Zone](#).
- Level location.
- [Slot](#) location

The physical location is a physical representation of where the [Slot](#) is located based on racking parameters, such as number of drawers/shelves and [Slots](#) per drawer/shelf, to enable users to easily locate the Target Location. If [Slotting](#) is not enabled, or no [Zones](#) mapped to the [Repository](#), [Zone](#) will be displayed as No-Alloc, [Slot](#) will display as zero.

Expanding the lower section Update Statistics displays information of when, where and who placed the [Volume](#) into a move to the Target Location. These values are set automatically on creation of the [Volume](#) and are non editable fields.

See Also

- [Repository](#)
- [Current Location](#)
- [Scanned Location](#)

From:
<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/object/volume_target

Last update: **2025/01/21 22:07**

