

# Volume Target Location

When a [Volume](#) is placed in a move from its' Current Location to another Location, that other Location is a Target Location.

Once the [Volume](#) is confirmed at the Target Location, the [Volume's](#) Current Location is updated to match the Target Location, removing the [Volume's](#) Move (M) [Flag](#) and Move Status.

If Slotting is enabled the Target Location will, when a Slot is assigned, include the Slot Allocation details as well.

Edit Volume: 000013L6

| Datasets | Attributes      | VeriScore™       | DR Strategies    | Options | Catalog |
|----------|-----------------|------------------|------------------|---------|---------|
| Identity | Target Location | Current Location | Scanned Location | Notes   | History |

Virtual Location

|            |               |
|------------|---------------|
| Repository | Offsite Vault |
| Slot       | 282           |

Physical Location

|      |        |
|------|--------|
| Zone | Rack C |
| Slot | 9.2    |

Update Statistics

When

|                |                                      |
|----------------|--------------------------------------|
| Date           | Monday, April 05, 2021 (63 days ago) |
| Time           | 15:25:09                             |
| UTC Offset     | 600 minutes                          |
| Time at source | Monday, April 05, 2021 - 15:25:09    |
| Time Zone      | AUS Eastern Standard Time            |

From

|              |                         |
|--------------|-------------------------|
| Machine Name | 127.0.0.1 (GazillaByte) |
|--------------|-------------------------|

Details

|                  |                                    |
|------------------|------------------------------------|
| Connection Count | 2,134                              |
| First Connection | Sunday, August 04, 2019 - 16:44:36 |
| Last Connection  | Tuesday, June 08, 2021 - 09:29:19  |
| Interface        | TMSS10SlotAllocation               |
| Operating System | Windows                            |

As

|           |      |
|-----------|------|
| User-ID   | doco |
| User Name | doco |

Save

Cancel

Help

The **Relative location** panel (A) displays:

- [Repository-ID](#) and [Description](#).
- Slot Number allocated.
- Maximum number of Slots assigned to the Target [Repository](#).

If slotting is not enabled, or no zones mapped to the [Repository](#), Slot number and maximum will

display as zero.

The **Absolute Location** (B) displays:

- The Zone-ID.
- Level location.
- Slot location

The absolute location is a physical representation of where the Slot is located based on racking parameters, such as number or drawers/shelves and Slots per drawer/shelf, to enable users to easily locate the Target Location. If Slotting is not enabled, or no Zones mapped to the [Repository](#), Zone-ID will be blank, level and Slot will display as zero.

Expanding the lower section **Update Statistics** (C) displays information of when, where and who placed the [Volume](#) into a move to the Target Location. These values are set automatically on creation of the [Volume](#) and are non editable fields.

## See Also

- [Repository](#)
- [Current Location](#)
- [Scanned Location](#)

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

[https://docs.tapetrack.com/object/volume\\_target?rev=1578360984](https://docs.tapetrack.com/object/volume_target?rev=1578360984)

Last update: **2025/01/21 22:07**

