

Volume Target Location

When a [Volume](#) is placed in a move from its' Current Location to another Location, that other Location is a Target Location.

Once the [Volume](#) is confirmed at the Target Location, the [Volume's](#) Current Location is updated to match the Target Location, removing the [Volume's](#) Move (M) [Flag](#) and Move Status.

If [Slotting](#) is enabled the Target Location will, when a [Slot](#) is assigned, include the [Slot](#) Allocation details as well.

Edit Volume: 000013L6

Datasets Attributes VeriScore™ DR Strategies Options Catalog

Identity Target Location Current Location Scanned Location Notes History

Virtual Location

Repository	Offsite Vault
Slot	282

Physical Location

Zone	Rack C
Slot	9.2

Update Statistics

When

Date	Monday, April 05, 2021 (63 days ago)
Time	15:25:09
UTC Offset	600 minutes
Time at source	Monday, April 05, 2021 - 15:25:09
Time Zone	AUS Eastern Standard Time

From

Machine Name	127.0.0.1 (GazillaByte)
--------------	-------------------------

Details

Connection Count	2,134
First Connection	Sunday, August 04, 2019 - 16:44:36
Last Connection	Tuesday, June 08, 2021 - 09:29:19
Interface	TMSS10SlotAllocation
Operating System	Windows

As

User-ID	doco
User Name	doco

Save Cancel Help

The **Virtual location** panel displays:

- Target [Repository](#).
- [Slot](#) Number allocated (if [Slotting](#) is enabled and [Volume](#) is allocated to a [Slot](#)).

If [Slotting](#) is not enabled, or no [Zones](#) mapped to the [Repository](#), [Slot](#) number will display as zero.

The **Physical Location** displays:

- The [Zone](#).
- Level location.
- [Slot](#) location

The physical location is a physical representation of where the [Slot](#) is located based on racking parameters, such as number of drawers/shelves and [Slots](#) per drawer/shelf, to enable users to easily locate the Target Location. If [Slotting](#) is not enabled, or no [Zones](#) mapped to the [Repository](#), [Zone](#) will be displayed as No-Alloc, [Slot](#) will display as zero.

Expanding the lower section **Update Statistics** (C) displays information of when, where and who placed the [Volume](#) into a move to the Target Location. These values are set automatically on creation of the [Volume](#) and are non editable fields.

See Also

- [Repository](#)
- [Current Location](#)
- [Scanned Location](#)

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://docs.tapetrack.com/object/volume_target?rev=1623114256

Last update: **2025/01/21 22:07**

