


Printing Zone Barcodes

Zone barcodes can be printed from TapeTrack TapeMaster using the TapeTrack Barcode Printer.

Identify what zone ID barcodes required to print by right-clicking the repositories, in the respective customer media types, and select Properties and then the Zones tab.


In the Zone Administration window under the heading **Zone** is the Zone-ID number and Zone description (in the format number:description). Record these details and close the window by the X at the top right or using the Cancel button.



From the main menu, select Administration→Zone Administration.

From the displayed zones, select the required zones (range select Shift+Click, Control+Click).

Right-click the highlighted zones and select Print→Labels to pass the barcodes through to the TapeTrack Barcode Printer.



The screenshot shows a web application window titled "Zone Administration". It has two tabs: "Zones" (selected) and "Allocations". Below the tabs is a table with the following columns: ID, Zone, Description, and Slots/Level. Each column has a search filter icon and a placeholder text "Enter text here". The table contains 11 rows of data, each with a unique ID, a color-coded name, a description, and a value of 10 for Slots/Level.

ID	Zone	Description	Slots/Level
@00001	Blue1	Blue 1	10
@00002	Blue2	Blue 2	10
@00003	Blue3	Blue 3	10
@00004	Blue4	Blue 4	10
@00005	Blue5	Blue 5	10
@00006	Yellow1	Yellow 1	10
@00007	Yellow2	Yellow 2	10
@00008	Yellow3	Yellow 3	10
@00009	Yellow4	Yellow 4	10
@00010	Yellow5	Yellow 5	10
@00011	Green1	Green 1	10


Editing Print Layout

Use the left window pane on the Barcode Printer to edit the print layout options to suit your requirements.

- Across: Number of barcodes to print across the page.
- Down: The number of barcodes to print down the page.
- Margins: Margins to be placed around the barcodes
 - Left: Left margin padding
 - Right: Right margin padding
 - Top: Top margin padding
 - Bottom: Bottom margin padding
- Appearance:
 - Separator Box: Adds a grey border around each Barcode to aid in separating individual Barcodes when manually cutting them out.
 - Preview Margins: Adds a preview of print boundaries to aid in confirming Barcode will print within a specified area.
 - QR Code: Adds a QR code to the Barcode label.
 - Include Human Readable: Adds text representation of Barcode to make it readable by Humans.
 - Font: Sets font for Human Readable content, does not alter Barcode.

Closing The Barcode Printer

To close the Barcode Printer, from the Main Menu select File → Exit or click the X at the top right of the window.



[barcode](#), [print](#), [tapemaster](#), [update doco](#)

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://docs.tapetrack.com/print_barcodes/zones?rev=1617601899

Last update:

2025/01/21 22:07

