


TapeMaster Configuration File

To modify TapeMaster, open TMSSMaster.cfg in a plain text editor such as Notepad.

TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

The config file has comments throughout the code to either disable the execution of unused code blocks or add explanation to the available functions. *Block quotes look like /* */, anything between these characters are treated as comments and not code. Anything after the characters // are treated as comments and not code for that line.*

==== Remove Slot Level Display ==== Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    /*
    variables = {
        TMSSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```



Remove comment tags /* & */ from above and below variables. Change the line of code

TMSSLEVELNAMES = "A,B,C";

to

TMSSNOLEVELSLOT = "true";

```

TMSSMaster.cfg - Notepad
File Edit Format View Help

options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    variables = {
        TMSSNOLEVELSLOT = "true";
    };

    showparent = true;
};

defaults = {

```

and save file. <note important>Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file or other file extension.</note> To check the modification was successful: Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below. Before modification - TapeMaster displaying Zone, shelf and slot.



Inventory DR Strategies Data Clusters Simple Management Uploaded Files Consignments

Volumes

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6.1]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10.10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10.10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

After modification - TapeMaster displaying Zone and shelf only.

Inventory DR Strategies Data Clusters Simple Management Uploaded Files Consignments

Volumes

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6]		CNO		Unspecified	Unassigned	Perman
000002L5	Rack_01 [10]		CGNO		Unspecified	Unassigned	Perman
000003L5	Rack_03 [10]		CNO		Unspecified	Unassigned	Perman
000004L5	Library		CnN		Unspecified	Unassigned	Perman
000005L5	Library		CnN		Unspecified	Unassigned	Perman
000006L5	Library		CEnN		Unspecified	Unassigned	Perman

<note important>If when opening TapeTrack TapeMaster you receive an error - **Failed to read configuration file (TMSSMaster.cfg): Line() - Syntax error** check the configuration file that you have used plain ASCII quotes (" ") and not rich text quotes (" ") and that the replaced text is correct.</note>

From:
<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/technote/config_file_tapemaster?rev=1541633764

Last update: **2025/01/21 22:07**

