

SetInitialRepository

Set the Current, Target and Scanned Repository value for newly added Volumes.

Phase

This instruction is used by the TapeTrack Synchronization Engine.

Syntax

SetInitialRepository(*repository*);

string *repository*;

repository	The initial Repository values for a new Volume.
------------	---



If the Media Type for the added Volume has an Initial Repository value set in its options, this value will override any value set by SetInitialRepository.

Example

Set the initial Repository values to LIBR.

```
<sxh> # # Set the initial Repository values to LIBR. SetInitialRepository("LIBR");
```

```
</sxh>
```

From:

<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://docs.tapetrack.com/engine/sync/setinitialrepository?rev=1539908980>

Last update: **2025/01/21 22:07**

