


Built In Repositories

TapeMaster has 3 built in [Repositories](#), which are hidden by default.

To display the hidden [Repositories](#), navigate to the Options tab in the [Media](#) Type Properties Window and set Show Built In Repositories to **true**. The [Repositories](#) **Initial**, **Next** and **Home** will be displayed in the [Repository](#) window.



Built-In [Repositories](#) often do not exist as locations, but they use settings in the Options Tab of the Volume Properties Window to dictate movements.

Built In Repository Functions

Initial Repository

If No Selection is set in the Default Repository field in the Media Type Properties Window's Options Tab, newly added [Volumes](#) will be allocated to the Initial [Repositories](#).

Edit Media: LTO Cartridge

Identity

Volume-ID Building

Options

Hide Media Type	False
Internal	True
Maximum Volumes	0
Maximum Repositories	0
Allowable Volume-IDs	
Default Media Type	False
Auto Simple Management	False
Auto Container	False
Stock Controlled	False
Auto Stock Selection	False
Relaxed Barcode Matching	False
No Move-back Warning	False
Lock Volumes	False
No HealthCheck	False
Show BuiltIn Repositories	True
Remove barcode suffix	
Barcodes use Modulo43	False
Default Repository	<No Selection>

Inventory

DR Strategies

Data Clusters

Simple Management


Uploaded Files

Consignments

Volumes

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
Enter text h...	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000002L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000003L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000004L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000005L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000006L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000007L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000008L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000009L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000010L5	Initial Repository		CnN		Unspecified	Unassigned	Permanent
000011L5	Initial Repository		Cn		Unspecified	Unassigned	Permanent
000012L5	Initial Repository		Cn		Unspecified	Unassigned	Permanent

Any other [Repositories](#) may be set as the default location for new [Volumes](#) by right-clicking the required [Repositories](#) and selecting Make Default Repository




Home Repository

Dragging and dropping [volumes](#) to the Home [Repository](#) places them into a move status to the [Repository](#) set as the Home Repository in the [Volume Properties Window Options](#) tab.


An example for using this function would be [volumes](#) returning from offsite storage back on-site and needing to be stored in different racks ([repositories](#)). Having the required rack set for each [volume](#) allows you to drag and drop all the [volumes](#) on the Home [Repository](#) and letting TapeTrack sort which [repository](#) each of the [volumes](#) belong in, saving you having to separate each group of [volumes](#) for each [repository](#) manually.

A [volume's](#) **Home Repository** can be set in the Volume Properties Window Options Tab.




or by right-clicking [Volumes](#) in the Volume List, then selecting [Special Operations](#), [Modify](#), and [Home](#)

Repository. Selecting a range of **Volumes** allows you to assign multiple **volumes** Home **Repository** in the one operation.



Select **Repository** from popup window drop-down box.



Next Repository

Drag and dropping **Volumes** to the next **Repository** places them into a move status to the **Repository** set as the Next **Repository** in the **Volume** Properties Window Options tab.

From:
<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://docs.tapetrack.com/master/built_in_repositories?rev=1571266937

Last update: **2025/01/21 22:07**

