


# Adding and Maintaining Volumes


## Adding Individual Volumes

To add an individual [Volume](#) either:

Right-click on a [Media Type](#) and select Add Volume.



or right-click in the Inventory window and select Add.



or click in the Inventory window and press Insert on the keyboard

This will open the Edit New Volume window.

In the Edit New Volume window enter the [Volume-ID](#) of the new [Volume](#) to be added. [Volume-ID](#)'s must be unique within a [Customer/Media Type](#) scope and must be between 1 and 10 alphanumeric characters long.

Volume Attributes

|             |      |                         |
|-------------|------|-------------------------|
| Customer-ID | US02 | Los Angeles Data Center |
| Media-ID    | LTO  | LTO Cartridge           |
| Volume-ID   |      |                         |

Save Cancel Help

Click Save to add [Volume](#).

## Adding Multiple Volumes


Adding multiple Volumes can be accomplished using several different methods.

- [Scanning Volumes using the "Scan To Add" process](#), best suited to adding small groups of Volumes with a scanner, keyboard or [GazillaByte CloudScan App](#).
- [Pasting in Volumes from Windows Clipboard or file](#), best suited to adding new Volumes from emailed or file lists of Volume-ID's.
- [Importing Volumes from Excel file](#), best suited to adding Volumes and additional data from Excel sheets.
- [Creating Volumes using the "Volume-ID Building" tool](#).
- Importing Volumes from your Backup Software with TMSS10Sync.
  - [Backup Exec](#)
  - [Commvault](#)
  - [Data Protector](#)


- [Netbackup](#)
- [Networker](#)
- [Tivoli Storage Manager](#)
- [VEEAM](#)

## Scan To Add

To add [Volumes](#) to your default [Repository](#) (or Initial [Repository](#) if no default is set) right-click in the Volume List, navigate to Special Operations, and select Scan → Scan to Add Volumes to open the Scan In window.



To add [Volumes](#) to a [Repository](#) other than your default, right-click the required [Repository](#) and select Scan → To Add and scan [Volumes](#) to be added.




Scan your Volume Barcodes using a Barcode scanner to add [Volumes](#) to TapeTrack.

Once all Volumes have been scanned, close the Scan In window by clicking the X at the top right corner.

## Paste Volumes To Add

Copy Volume-ID's to windows clipboard.

To add [Volumes](#) to your default [Repository](#) (or Initial [Repository](#) if no default is set) right-click in the Volume List, navigate to Special Operations, and select Scan → Scan to Add Volumes to open the Scan In window.



To add [Volumes](#) to a [Repository](#) other than your default, right-click the required [Repository](#) and select Scan → To Add and scan [Volumes](#) to be added.

TapeTrack TapeMaster™ (GazillaByte)

File Administration Favorites Tools View Help

Customer Filter

**GazillaByte - Production**

- US00 - United State
- US01 - New York
- US02 - Los Angeles
- CONT - Contingency
- LTO - LTO Cartridge
- US03 - North Carolina

**Inventory** **DR Strategies** **Data Clusters** **Simple Management** **Uploaded Files**

**Volumes** **Los Angeles Data Center** **LTO Cartridge**

| ID             | Current Location     | Target Location     | Next Move     | Description     |
|----------------|----------------------|---------------------|---------------|-----------------|
| Enter text ... | Enter text here      | Enter text here     | Enter text... | Enter text here |
| 000006L6       | Library              | Offsite Vault [...] | Friday, No... | Monthly         |
| 000008L6       | Library              | Offsite Vault [...] | Permanent     | Weekly          |
| 000010L6       | Offsite Vault [0...] |                     | Permanent     | Scratch         |
| 000011L6       | Offsite Vault [0...] |                     | Permanent     | Weekly          |
| 000012L6       | Library              |                     | Permanent     | Scratch         |
| 000013L6       | Library              |                     | Permanent     | Scratch         |
| 000014L6       | Library              | Offsite Vault [...] | Permanent     | Weekly          |
| 000015L6       | Library              |                     | Permanent     | Scratch         |
| 000016L6       | Library              |                     | Permanent     | Scratch         |
| 000017L6       | Library              |                     | Permanent     | Scratch         |
| 000018L6       | Library              |                     | Permanent     |                 |
| 000019L6       | Library              |                     | Permanent     |                 |
| 000020L6       | Library              | Offsite Vault [...] | Friday, De... | Weekly          |
| 000021L6       | Library              |                     | Permanent     |                 |
| 000022L6       | Library              |                     | Permanent     |                 |
| 000023L6       | Library              |                     | Permanent     |                 |

Total Items 1,589 Total Selected 1 First Selection 1

**Repositories**

Gemtrac Library Offsite Vault

Connection 127.0.0.1 uses AES 256 bit encryption

Click the Clipboard icon on the Scan Window to paste in Volume-ID's.

Scan to add new Volumes



000158L5

Messages (14)

| Barcode  | Customer                   | Media Type    | Volume-ID | Message    | Count |
|----------|----------------------------|---------------|-----------|------------|-------|
| 000157L5 | North Carolina Data Center | LTO Cartridge | 000157L5  | Request OK | 1     |
| 000156L5 | North Carolina Data Center | LTO Cartridge | 000156L5  | Request OK | 1     |
| 000155L5 | North Carolina Data Center | LTO Cartridge | 000155L5  | Request OK | 1     |
| 000154L5 | North Carolina Data Center | LTO Cartridge | 000154L5  | Request OK | 1     |
| 000153L5 | North Carolina Data Center | LTO Cartridge | 000153L5  | Request OK | 1     |
| 000152L5 | North Carolina Data Center | LTO Cartridge | 000152L5  | Request OK | 1     |
| 000151L5 | North Carolina Data Center | LTO Cartridge | 000151L5  | Request OK | 1     |
| 000150L5 | North Carolina Data Center | LTO Cartridge | 000150L5  | Request OK | 1     |
| 000149L5 | North Carolina Data Center | LTO Cartridge | 000149L5  | Request OK | 1     |
| 000148L5 | North Carolina Data Center | LTO Cartridge | 000148L5  | Request OK | 1     |
| 000147L5 | North Carolina Data Center | LTO Cartridge | 000147L5  | Request OK | 1     |
| 000146L5 | North Carolina Data Center | LTO Cartridge | 000146L5  | Request OK | 1     |
| 000145L5 | North Carolina Data Center | LTO Cartridge | 000145L5  | Request OK | 1     |
| 000144L5 | North Carolina Data Center | LTO Cartridge | 000144L5  | Request OK | 1     |

Advanced Capture





Defaults

|             |      |
|-------------|------|
| Customer-ID | US03 |
| Media-ID    | LTO  |

Options

|                   |       |
|-------------------|-------|
| Save Defaults     | True  |
| Enable Sounds     | True  |
| Edit              | *     |
| Multiline Records | False |
| Auto Hash 20+     | False |

RFID Options

|                  |   |
|------------------|---|
| SSP RFID Port    | 0 |
| SSP Barcode Port | 0 |

Once all Volumes have been scanned, close the Scan In window by clicking the X at the top right corner.

## Deleting Volumes

For information on deleting Volumes see [Deleting Volumes](#)

[update doco](#), [scan](#), [master](#)

From:  
<https://docs.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
<https://docs.tapetrack.com/master/volumes?rev=1676412819>

Last update: **2025/01/21 22:07**

